Installing Novell Clients

The Novell[®] ClientTM Setup utility installs the client software. When you use this utility, you can select the client you want to install from a list of available clients.

PREREQUISITES

- LONG.NAM installed on NetWare[®] servers for long file names in Windows* 95/98 and Windows NT*
- Connection to a NetWare network
- Applicable server patches installed

HARDWARE REQUIREMENTS

Windows 95/98

- □ 486 processor or higher
- Minimum 28 MB free disk space
- Minimum 16 MB RAM

Windows NT 4.0

Minimum hardware requirements of Windows NT 4.0

DOS and Windows 3.1x

- □ 386 processor or higher
- □ Minimum 15 MB free disk space
- Minimum 8 MB RAM
- A memory manager

SOFTWARE REQUIREMENTS

One of the following client operating systems:

- Windows 95/98 with Windows 95 or Windows 98 CD-ROM or the Windows .CAB files
- Windows NT 4.0
- □ A DOS operating system such as:
 - Novell DOS 7
 - MS-DOS* 5.x or 6.x
 - PC-DOS 5.x, 6.x, or 7.0
 - Windows 3.1*x* or Windows for Workgroups 3.11

PROCEDURE

||||**1**]

Note: Documentation explaining network installation methods is available in the online documentation on the Novell Client CD-ROM. This documentation can be viewed on 32-bit workstations and is available from the Setup utility.

1. Insert the Novell Client CD-ROM.

If the Setup utility does not start automatically, run WINSETUP.EXE from the root of the CD-ROM.

- 2. Click a language for the installation.
- 3. Click the platform you want to install.
- **4.** Click Install Novell Client, and then follow the on-screen instructions.

- 5. Do one of the following:
 - If you have a NetWare 4TM network or you are using IPXTM protocols, click Custom to configure the Client for an IPX network, and then select the IPX protocol.
 - If you have a NetWare 5TM network and you are using IP protocols, accept the Typical installation.

Note: The Novell Client for DOS and Windows 3.1*x* is an IPX-only client. If you are connecting to a NetWare 5 IP-only server, the server must be running Compatibility Mode (SCMD.NLM) and the network must have a Migration Agent on a NetWare 5 server.

6. To finish installing the Client, follow the on-screen instructions.

SOFTWARE INCOMPATIBILITIES

Windows 95/98

- Microsoft* Client for NetWare networks
- Microsoft file and printer sharing for NetWare networks
- □ Microsoft Service for Novell Directory Services[™]
- Novell NetWare workstation shell 3.x (NETX)
- □ Novell NetWare workstation shell 4.0 and later (VLM[™])
- □ Novell IPX ODI[™] protocol

Windows NT

 Incompatibilities listed in the readme for this Client (WINNT.TXT)

Copyright and Trademarks

Copyright © 1998 Novell, Inc. All rights reserved.

Novell and NetWare are registered trademarks of Novell, Inc. in the United States and other countries. Internetwork Packet Exchange and IPX, NetWare 4, NetWare 5, Novell Client, Novell Directory Services and NDS, Open Data-Link Interface and ODI, and Virtual Loadable Module and VLM are trademarks of Novell, Inc.

Microsoft, MS-DOS, Windows, and Windows NT are registered trademarks of Microsoft Corporation.